

Upgrading the distribution rendering (Pixel) server

1. Log on as administrator (not Araxi) to the distribution rendering (Pixel) server.
2. Run the **Distribution Server Installation** wizard:
 - a. On the distribution server, open a command-prompt window, and type `net use * \\<ServerIPAddress>\AraxiHome`
(`<ServerIPAddress>` is the IP address of the main InSite Creative Workflow server).
 - b. Note the drive letter that the system assigned (Usually Z).
 - c. At the command prompt, type `cd /d <DriveLetter>:\TWAM\support\bin`
(`<DriveLetter>` is the drive letter that the system assigned).
 - d. At the command prompt, type `Setup_PixelServer.exe`
The **Distribution Server Installation** wizard starts.
Note: Depending on your security settings, the Open Files Security dialog box may appear several times throughout the process, click **Run** each time.
 - e. On the Drive Selection window, complete the following options:
 - For the **Distribution Server Root**, select the system drive (C).
 - For the **Temp Root**, select the drive where the Temp directory resides (C).
 - f. Click **OK**.
 - g. On the InSite Server IP window, in the **IP Address** box, type the IP address of the InSite Creative Workflow server, and click **OK**.
 - h. On the Setup_PixelServer window, perform the following actions:
 - If the InSite Creative Workflow server is in a DMZ configuration, click **Yes**
 - i. On the TwAm Server Name window, type the name of the main InSite Creative Workflow server and click **OK**
 - ii. On the Login window, type the password for the ARAXI account, and click **OK**.
 - If the InSite Creative Workflow server is not in a DMZ configuration, click **No**.
 - i. On the Login window, type the password for the ARAXI account, and click **OK**.
 - i. In the Open Files Security dialog box, click **Run**.
Note: Depending on your security settings, this dialog box may appear several times, click **Run** each time.
3. On the Setup_PixelServer window, click **OK** to complete the installation.
4. In the Distribution Server Setup window, click **Close**.
5. When you are prompted, restart the server.